

How to configure Windows 98 to connect to EDS*ELIT Dial-Up Server

EDS*ELIT Dialup Server is a PPP server allowing ELIT users to connect to EDS*ELIT network via modem. Users connected to EDS*ELIT Dial-Up Server can communicate with their ELIT trading partners using TCP/IP based protocols such as E5, FTP, ELIT TCP/IP and others, can use web browser to manually navigate transmissions of messages and can use ELIT File Tracking for inquiring about ELIT transmissions.

In order to utilize EDS*ELIT Dial-Up service one must first configure his/her PC. This can be done by creating a new Dial-Up Networking. On Windows 98 start Dial-Up Networking by double clicking the icon representing it, double click on 'Make New Connection' icon and enter 'EDSELIT' as the name for the new computer you are dialing. In the same window select the modem you want to use from the pull down menu. Proceed by clicking 'Next>' button. In the next window enter the phone number to dial: (248) 276-2223 and proceed to the next window by clicking 'Next>' button. Next window should confirm that you successfully created a new Dial-Up Networking connection. That is it! Click on 'finish'. There is no need to edit more properties as default settings should work fine with the EDS*ELIT Dial-Up Server. For reference purposes all Dial-Up Networking configuration windows are included at the end of this document.

To establish a network connection with EDS*ELIT network via Dial-Up Networking double click EDSELIT icon from Dial-Up Networking window. In the 'Connect To' window enter 'edselit' in User name field and 'dialup' in Password field. You can also select 'Save password' check box if you want to skip this step of being asked for the user name and password in the future. User name and Password will never change and are not used here for authentication purposes. The actual authentication and authorization will be done by the ELIT service used. Once connected to the EDS*ELIT network, you can start using EDS*ELIT services by connecting to EDS*ELIT server using an application of your choice, i.e. web browser, ftp, ELITclient.

EDS*ELIT TCP/IP Services:

E5 Web Site	Production	http://www.elit.eds.com
FTP	Production	ftp://ftp.elit.eds.com

Configuration Summary:

Server Type: PPP

Phone Number: (248) 276-2223

User name: edselit, Password: dialup

IP address: assigned by server (range from 199.228.97.8 to 199.228.97.31)

Domain Name Server: assigned by server (206.122.227.35)

